

Release Notes 2012-05-21

Config db ntf: 20120521084500
 Analyze db ntf: 20120521084500
 Windows Version: 2.6.0 :: MAC OS X Version: 2.0.36 :: Linux Version: 2.0.38
 Eclipse Plugin:


Major Improvements: Added optional progress bar display during client shutdown, Added new option to significantly optimize Eclipse client configuration backups (also fixes roaming of open composite application tabs, e.g. Mailfile, Calendar, ...), Added four new config variables, Fixed file- and directory link detection problems keeping the Cleanup Job from working, Licensing now explicitly restricts backup to fileset /network share only to licenses covering MarvelClient Roaming

General Notes	
	<p>Supported IBM Lotus Notes releases: 5.x, 6.x, 7.x, 8.x, up to 8.5.3 (Administrators need at least IBM Lotus Notes 7.x on Windows or Linux)</p> <p>Supported client-side operating systems: Microsoft Windows NT4 (>=SP2), 2000, XP, 2003, 2008, Vista, 7, and Citrix/WTS, Apple Intel Mac OS X Leo</p> <p>Supported server-side operating systems: any supported by IBM (operating system independent)</p> <p><i>NOTE: Support is limited for platform and release combinations not supported by IBM</i></p>
	<p>Linux & Mac OS X: Skinning, Realtime, Zip/Unzip and Attachment Blocking are not available on Linux or Mac OS X;</p> <p>Citrix, Linux & Mac OS X: Upgrade is only available on Windows (=not on Citrix, Linux or Mac OS X)</p> <p>MarvelClient on Mac OS X and Linux does not support the runtypes "After Login - Before Sync", "After Login - After Write" and "On first server access" supported runtime, e.g. "After Login"</p>
I M P O R T A N T N O T E S	<p>This release contains select important updates highlighted in red</p>
Configuration Database	
F I X	Fixed a problem with a wrong hide/when formula erroneously hiding the "Change Existing" option when either Send AND/OR Receive were not checked
C H A N G E	Removed non-supported runtimes from backup action (essentially all before login runtime moments which were displayed although not working)
C H A N G E	The [Advanced\Mailbased Installation] menu option has been re-labelled [Advanced\Installation] since it not only supports deployment by email but also
C H A N G E	Changed the Eclipse Roaming backup action example to use the suggested regular expression (see 2.6.0 DLL change documentation below)
C H A N G E	The "Disable view updates as background task" was erroneously inverted (=adding the option to the enabled list would actually enable view updates, rather than that you must resave any user preferences management action)
C H A N G E	The view [MarvelZip\Configuration] has been changed to only show configuration documents for MarvelZip/Unzip and any INI Management actions the

E N H A N C E M E N T	Added an action example in the (MarvelClient) [Roaming] Category for configuring the new optional shutdown progress bar
E N H A N C E M E N T	Added an action example [Delete cache.ndk (once only) if larger than 50 MB]
E N H A N C E M E N T	Added an action example [Run compact for all local databases including templates for ODS upgrade in background once]
Analyze Database	
F IX	Fixed a problem where the HW/SW inventory agent contained test code which hardcoded the analyze (upload) database to (Local)!!panagenda\analyze_dev.nsf
MarvelClient Upgrade	
C H A N G E / E N H A N C E M E N T	<p>MarvelClient Upgrade 2.6 is now available with several enhancements - the following list of changes and enhancements only contains the most important</p> <ul style="list-style-type: none"> MarvelClient (MC) Upgrade is now configured through its own .ini file rather than fiddling around in a batch file MC Upgrade now shows a system modal, movable progress bar dialog instead of the previous "DOS box progress display" <ul style="list-style-type: none"> MC Upgrade now supports configurable <ul style="list-style-type: none"> wait period until termination of (again configurable) processes (e.g. hanging Notes client processes) removal of shortcuts before beginning of an upgrade so as to prevent users from starting the client whilst it is being uninstalled automatic data directory migration from source to target (e.g. when switching from single to multi-user clients or from network share (fileset) includes smart data moving (=copying data only if necessary, otherwise performing an OS directory/file move; in case of copying the data from clean up the old data directory) Optional removal of registry keys before uninstalling and before installing products/fixpacks/etc. Simulation of an upgrade (with simulation enabled, MC Upgrade will only log what would happen, but not actually execute any changes) Optional debug dialog boxes (=MC Upgrade will display various detail dialog boxes during the Upgrade/Install/Uninstall/Cleanup etc. process) Optional restore of network drive mappings when switching from the current user to an admin account
.DLL Updates (Windows)	

C H A N G E (2 . 6 . 0)	For trials/evals of MarvelClient, the zip checkbox is now disabled by default when attaching files
C H A N G E / E N H A N C E M E N T (2 . 5 . 1 8)	The availability of notes:um_server / notes:umserver has been improved; in case no details are resolved from the public addressbook using a location
E N H A N C E M E N T (2 . 5 . 1 8)	Added a new config variable resulting in the current OS language locale according to http://msdn.microsoft.com/en-us/goglobal/bb964664
E N H A N C E M E N T (2 . 5 . 1 8)	Added three new config variables , , to allow for easier platform conditions (e.g. a numeric condition [>= [6] would query for Windows 7 and up; to be p R2); for further details on operating system versions see http://msdn.microsoft.com/en-us/library/windows/desktop/ms724832%28v=vs.85%29.aspx

E N H A N C E M E N T (2 .5 .1 8)	Added support for Windows 8 detection (<os:version_string>, <os:build>, <os:major>, <os:minor>)
E N H A N C E M E N T (2 .5 .1 8)	Improved logging for DLL updates; in case a DLL update fails, log.xml will now contain further details
E N H A N C E M E N T (2 .6 .0)	Added seperator lines into log.xml for easier reading of runtimes (durations) and end of log sections; the following screenshot shows an example:

E N H A N C E M E N T (2 .6 .0)	If a duplicate URL in desktop (workspace) prevents an icon from being created or read, MarvelClient now logs a warning into log.xml
E N H A N C E M E N T (2 .6 .0)	Added a new variable <notes:version_number> which consists of MajorVersion*1000000 + MinorVersion*10000 + QMRNumber*100 + QMUNumber This new variable allows for easier numeric conditions querying notes versions, e.g. 8050301 = 8.5.3 FP1, whereas 8050300 = 8.5.3
E N H A N C E M E N T (2 .6 .0)	<p>Added optional progress bar display when shutting down Notes: <mc:pbar_shutdown_enabled> = true 1 yes enables progress bar display upon client shutdown; this is particularly valuable for MarvelClient Roaming c progress bar is shown during client shutdown</p> <p>If enabled, the following screenshot shows the default progress bar configuration displayed during client shutdown:</p> 
	<p>The first progress bar shows a section counter - in essence, processing of actions in each runtime moment is spread out across "sections" (for example /objects); these do not translate to runtime moments or similar, just in case you start counting and comparing with something familiar ;-)</p> <p>The second progress bar shows number of executed actions (including conditions); note that even though the progress bar is currently only available a actions from starting the client until shutdown, not just number of shutdown actions.</p> <p>The third progress bar shows the number of subactions within each currently processed action; for a backup action this would be a subaction as per ba</p> <p>Note that the title of the progress bar can be customized as follows: <mc:pbar_shutdown_header> = Your Titlebar Text By default the progress bar is titled "Please wait..."</p> <p>In addition, the progress bar can be further configured as follows: <mc:pbar_textshow> = true 1 yes shows section/action/subaction details as text - note that this text can NOT be customized. <mc:pbar_limitlevel> = 0 1 2... limits the number of progress bars being displayed (offset being 0!); the default is not set (=display all progress bars, wh can reduce the number of progress bars being displayed to e.g. 2 (by setting mc:pbar_limitlevel to 1) or 1 (by setting mc:pbar_limitlevel to 0).</p>
.dylib Updates (Mac OS X)	

- N o c h a n g e s -	- No changes -
.so Updates (Linux)	
- N o c h a n g e s -	- No changes -